

Customization of Alerting and Dashboards in Health Insights

© 2020–2021 Cisco Systems, Inc. All rights reserved. **FOR INTERNAL USE ONLY**

Health Insights releases 3.x use [InfluxDB](#), Kapacitor Stack for achieving alerting functionality in Health Insights KPIs

Steps for Customization

- [Export a stock / custom KPI, will be used as starting points](#)
- Edit the kapacitor TICK script and/or dashboards with changes
- Update KPI json with metadata for the changes above
- Re-Import the KPI into Crosswork, and test.
- Use this document in addition to the following [Health Insights Developer Guide](#)
- This is an iterative process until the desired result is achieved

<https://developer.cisco.com/docs/crosswork/#!custom-kpis>

Anatomy of a KPI

Refer to the KPIs made available on the [Github](#) for the stock kpis included as part of Crosswork release.

<https://github.com/CiscoDevNet/Crosswork-KPI>

KPI consists of a json file that captures the `Metadata`, `Sensor list`, one or more `Alerting logic` (pointer to the TICK files) and one or more `Dashboards` for visualization of data and alerts.

Here is an example KPI for [Memory utilization](#)

Metadata

```
{
  "kpi_id"           : "pulse_memory_utilization",
  "kpi_name"         : "Memory utilization",
  "category"         : "Memory",
  "summary"          : "Monitors memory usage across route processor and line cards on routers",
  "details"          : "Monitors memory usage across route processor and line cards on routers; generates an alert",
  "sensor_type"      : "YANG_MDT",
  "module_and_revision": "Cisco-IOS-XR-nto-misc-oper:2015-11-09"
}
```

Sensor List

Here we can see the settings related to default, minimum and max cadences that can be customized.

```
{
  "sensor_groups": {
    "sensor_group": [
      {
        "cadence": {
          "default": 120,
          "min": 10,
          "max": 900,
          "increment": 10
        }
      }
    ]
  }
}
```



```

    "value": "Pulse-memory-utilization-raw.json",
    "label": "Raw"
  }
]
}
}

```

Anatomy of Alerting

Alerting logic implemented as a TICK script is executed using `Kapacitor` on `robot-astack-kapacitor` docker container. Each KPI can have zero or more of these and are installed as `tasks` on kapacitor. These tasks are installed per KPI `profile`, `script`. And can be seen on kapacitor using `kapacitor list tasks` command. These tasks will have names following a scheme as follows...

```
cw.pulse_<profile_id>_<script_id>
```

Example: `cw.pulse_core_pulse_cpu_utilization`

Kapacitor can execute these tasks as `Stream` or `Batch` jobs and for the most part Health Insights will be using stream tasks.

TICK script can be represented as a `Flow Diagram`. Flow Diagram has nodes and the data stream flows one node to another node, each node does a specific action on the data stream. A data point in the stream has set of keys and timestamp identifying the point uniquely in time and from a specific network entity. And each point has as many values as the `InfluxDB` measurement this Tick script is processing the data from.

Here is the [TICK Script](#) for this Memory Usage KPI

Please refer to [TICK script reference](#) for additional details on the syntax and specification

Basic structure of the TICK script or the Flow Diagram are as follows...

- **A set of variables**
 - Some of these are exposed via UI and some are internal and some are fixed and should not be modified for customization
 - Some of these variables can be updated to have a certain default value and can be used for customization

```

//KPI_INTERNAL KPI ID of the kpi this TICKscript measures
var kpi_id = 'pulse_memory_utilization'

//KPI_INTERNAL Alert ID for this KPI Alert event
var alert_id = 'pulse_memory_utilization'

//KPI_INTERNAL Alert message format string
var alert_message = '{{ .Level }} : {{ index .Tags "node-name" }} Memory Utilization: {{ index .Fields "kpi_'

//KPI_INTERNAL Clear message format string
var clear_message = '{{ .Level }} : {{ index .Tags "node-name" }} Memory Utilization: {{ index .Fields "kpi_'

//KPI_INTERNAL Measurement in influxDB to retrieve the data from
var measurement = 'Cisco-IOS-XR-nto-misc-oper:memory-summary/nodes/node/summary'

//KPI_INTERNAL Optional where filter expression to filter data stream before passing for transformation
var where_filter = lambda: TRUE

// KPI_INTERNAL filter var to filter data only related to kpi profile id
var where_producer = lambda: strContains("ProfileIDs", profile_id)

//KPI_INTERNAL Optional list of group by dimensions
var groups = ['Producer', 'node-name']

```

```
//KPI_INTERNAL Lambda expression to reduce raw data to KPI
var stream_eval_lambda = lambda: (1.0 - "free-application-memory"/"system-ram-memory") * 100.0

//KPI_THRESHOLDS (Critical Alert Threshold) Generates an alert when the data sample does not fall within the
var crit_threshold = 2.0

//KPI_THRESHOLDS (Warning Alert Threshold) Generates an alert when the data sample does not fall within the
var warn_threshold = 2.0

//KPI_THRESHOLDS (Clear Threshold) When a data sample falls within the number of standard deviations from the
var clear_threshold = 2.0

//KPI_THRESHOLDS (Activation Threshold) Values must exceed the activation threshold to generate a standard deviation
var activation_threshold = -1.0

//PULSE_RUN_TIME (Downsample Factor) Down sample factor for alert evaluation applied on data stream (Default
var downsample_factor = 1
```

`kpi_id`, `alert_id` is something you may not want to change as they need to match the `kpi_id` from `kpi json` file, else it will break some of the functionality.

• Input Data Query, Filter, Grouping and Down Sampling

- This section of the Flow Diagram shows how input data stream is defined
- From measurement, filter out any data point that is not be processed for Alerting
- Group the series by a set of keys so that alerting is for a given uniq network element
 - Example: `group-by node-name` will do memory utilization per `RP/Linecard`
 - Note that the keys and their names are part of the `YANG` or `MIB` model itself and these are called as `tags` in `Influx` terminology. Refer to the model for the keys that would be applicable for a certain `xpath`
- Customization here can be done by changing the variables `where_filter` and `groups`

```
var data = stream //stream0
|from() //from1
  .measurement(measurement)
  .where(where_producer)
  .where(where_filter)
  .groupBy(groups)
  .quiet()
|sample(downsample_factor) //sample2
```

`lambda` is a keyword used to indicate mathematical or logical expression and is a short for a function call.

We are using `lambda` expression to filter the data stream, and in this example we are saying consider only data points where `system-ram-memory` is > 8GB. Same goes with `groups` which is a list of keys and one has to be careful as if fewer keys are used then we need to use aggregation functions in next Flow Diagram nodes.

`Downsample` is exposed via the UI and not needed in any customizations as it can be changed while creating `KPI Profile`

```
//KPI_INTERNAL Optional where filter expression to filter data stream before passing for transformation
var where_filter = lambda: "system-ram-memory" > 80000000

// KPI_INTERNAL filter var to filter data only related to kpi profile id
var where_producer = lambda: strContains("ProfileIDs", profile_id)

//KPI_INTERNAL Optional list of group by dimensions
var groups = ['Producer', 'node-name']
```

• Transform to KPI Stream

- This section of the Flow Diagram shows how input data stream after it was filtering and grouped to multiple series, transformed to KPI Stream.

- The input points would contain a set of keys (`node-name` in this example) and these values, `ram-memory` , `free-physical-memory` , `system-ram-memory` , `free-application-memory`
- `lambda` expression is used to pick only select field or any other math computation
- `lambda` is a short expression instead of a full function(), please see [Kapacitor Documenation](#)
- To customize the kpi expression, modify the variable `stream_eval_lambda` , in this example its set to `lambda: (1.0 - "free-application-memory"/"system-ram-memory") * 100.0` to compute the percentage memory utilization
- **Note:** all the data types of the values used in the expression has be of the same data type. as a practice we are using float type for all numbers. Expression can also have string processing as its done in some of the stock KPIs
- From this node onwards only values available are the keys and `kpi_stream`

```
// Node: transform
// Input: data
// Output: kpi_stream
// Details: takes raw data and transforms it to kpi based on the stream_eval_lambda funtion
var transform = data
|eval(stream_eval_lambda) //eval3
.as('kpi_stream')
.quiet()
```

• Alert Logic

- This section of the Flow Diagram has mainly three parts and varies from master template to template_vars
- Please refer to the [Health Insights Developer Guide](#) for different types of logic that is exposed using KPI wizard
- **Section 1**, to handle post processing of the `kpi_stream` before alerting comparisons like taking a first order derivative, standard deviation, summarizations like distinct count etc.
- Here is an example of standard deviation based method, and this section for customization would mean that that you are building a new template and reach out to Development team for any guidance here.

```
// Node: stream_sd
// Input: transformed data
// Output: Sigma, alert_duration, clear_duration
// Details: Takes the transformed kpi data and identifies how many SDs away the sample is from mean
// And keeps track of how long the value is in alert or clear condition
var stream_sd = transform
|eval(lambda: sigma("kpi_stream")) //eval4
.as('sigma')
.keep('kpi_stream', 'sigma')
|default() //insert the thresholds into the data stream //default5
.field('crit_threshold', crit_threshold)
.field('warn_threshold', warn_threshold)
.field('clear_threshold', clear_threshold)
.field('activation_threshold', activation_threshold)
.tag('kpi_id', kpi_id)
.field('alert_src', 'TICK')
.tag('profile_id', profile_id)
```

- **Section 2**, to handle the Critical/Warning check and write alerts, checks are made with expression `"sigma" >= warn_threshold` and `"sigma" >= crit_threshold`
- `crit_threshold` and `warn_threshold` and other thresholds have some default values but are exposed using UI and can be changed during creation of KPI Profile . However, the default values can be customized here by changing variable assignments.

```
//KPI_THRESHOLDS (Critical Alert Threshold) Generates an alert when the data sample does not fall within the nu
var crit_threshold = 2.0

//KPI_THRESHOLDS (Warning Alert Threshold) Generates an alert when the data sample does not fall within the numbe
var warn_threshold = 2.0

//KPI_THRESHOLDS (Clear Threshold) When a data sample falls within the number of standard deviations from the mea
var clear_threshold = 2.0
```

- **Note** the `alert_message` used here which is a templated string in the list of variable we had in the very first section of this `TICKscript` which can be used to for customizing the message.

```
//KPI_INTERNAL Alert message format string
var alert_message = '{{ .Level }} : {{ index .Tags "node-name" }} Memory Utilization: {{ index .Fields "kpi_stre

//KPI_INTERNAL Clear message format string
var clear_message = '{{ .Level }} : {{ index .Tags "node-name" }} Memory Utilization: {{ index .Fields "kpi_stre
```

- Here is the snippet for the Alerting section

```
/ Alerting Node for warning and critical
// Input: stream_sd
// Output: Warning and critical alerts
// TODO need to understand the exact format the ASTACK requires the alerts to be
// generated and posted
stream_sd
|alert() //alert6
    // Warning on warning threshold
    .warn(lambda: ("sigma" >= warn_threshold AND ("kpi_stream" >= activation_threshold AND activation_thres
    // Critical on critical threshold
    .crit(lambda: ("sigma" >= crit_threshold AND ("kpi_stream" >= activation_threshold AND activation_thres
    .stateChangesOnly()
    .levelTag('level')
    .id(alert_id)
    .idField('id')
    .message(alert_message)
    .messageField('msg')
|where(lambda: "level" != 'OK') //filter OKs out //where7
|influxDBOut() //influxDBOut8
    .database(alerts_db)
    .retentionPolicy(alerts_rp)
    .measurement(alerts_meas)
    .tag('state', 'alert')
```

- **Section 3**, to handle the Clear condition and write alerts
- we can customize the `clear_message` to suite the need

```
// Alerting Node for clear condition
// Input: stream_sd
// Output: clear alerts
// TODO need to understand the exact format the ASTACK requires the alerts to be
// generated and posted
stream_sd
|alert() //alert9
    //info on clear threshold
    .info(lambda: ("sigma" < clear_threshold))
    .stateChangesOnly()
    .levelTag('level')
    .id(alert_id)
    .idField('id')
    .message(clear_message)
    .messageField('msg')
|where(lambda: "level" != 'OK') //filter OKs out //where10
|influxDBOut() //influxDBOut11
    .database(alerts_db)
    .retentionPolicy(alerts_rp)
    .measurement(alerts_meas)
    .tag('state', 'clear')
```

- The stock kpis may have additional templates and this document is to explain how one can export and use it as a starting point for customization. Refer to <https://developer.cisco.com/docs/crosswork/#custom-kpis/health-insights-stock-kpis>

• Best practices and other tips

- when exporting the stock kpis, `kpi_id` will have `pulse_` as prefix and is reserved for stock kpis and custom KPI would need to change this `kpi_id` not to use `pulse_` prefix
- `kpi_id` value in `kpi.json` is referenced in `TICKscript` and `Dashboards` remember to update it across all the files
- `alert_id` value needs to have `kpi_id` as prefix in order for Health Insights to quickly query for all alerts related to the KPI
- KPI `json` and Dashboard files validate that they are properly formed `json` files before testing

- **Debugging Changes to Alerting**

- After making changes to the alerting logic ensure you are validating the following, `.json` files should be checked against a `json-lint` for any errors. Validate that any files referenced in `kpi.json` are present
- Import the KPI and fix any errors from Crosswork, Create a KPI profile and enable it on a device where this `kpi` would work.
- Validate that KPI enable is successful, this would indicate that `TICK` script has not syntax issues and a `kapacitor` job is created
- If the above step fails, check the errors in the job details or log into Crosswork and use `kapacitor` CLI command in `robot-astack-kapacitor` container for errors

```

'''
kapacitor list tasks
tail /var/log/robot/kapacitor_stdout
tail /var/log/robot/kapacitor_stderr

```